



# **Release Notes**

Studio UG 4.1



© Copyright 2025 Datamine Software

All Rights Reserved Confidential and Proprietary

Published: 25 November 2025

#### **Legal Disclaimer**

The product described in this documentation may be connected to, and/or communicate information and data via, a network interface, which should be connected to a secure network. It is your sole responsibility to ensure a secure connection to the network and to establish and maintain appropriate measures (such as but not limited to the installation of firewalls, application of authentication measures, encryption of data, installation of antivirus programs, etc.) to protect the product, the network, your systems, and the interface against any kind of security breach, unauthorised access, interference, intrusion, leakage, damage, or corruption or theft of data. We are not liable for damages or losses related to any such security breach, unauthorised access, interference, intrusion, leakage, damage, or corruption or theft of data.





## **Contents**

Overview	5
Further Information	5
Studio UG 4.1 Release Notes	6
DTS Compatibility	6
MSO 5.0	6
Haulage Network Scheduling	7
Dependency Animation	8
Preparation Panel	8
Outline Validation	8
Leapfrog Data Import	9
Multiple File Loads	9
Legend Tools Update	10
Geosoft® Driver	10
License Services Security	10
Safer Scripting	11
Ribbon Standardization	12
Other Command & Process Updates	12
Early Access Features	13
All Improvements	15
Commands & Processes	15
Utilities & Supporting Services	19
Defect Fixes	21
Studio UG 4.0.1 Release Notes	25
Improvements	25
Defect Fixes	25
Studio UG 4.0 Release Notes	26
Scheduler Compatibility	26
Key Improvements	26

	New Datamine File Format	26
	Datamine Task Scheduler	27
	Stope Reconciliation Automatic Areas	28
	Dependency Prefilter	28
	Variable Autolayout Translations	28
	Plots Overhaul	29
	3D Window Improvements	29
	Filled Wireframe Intersections (Preview)	30
	Text Importer	31
	Datamine File Tags	31
	New Processes	32
All Im	provements	33
	Commands & Processes	33
	User Experience	36
	Utilities & Supporting Services	37
	Documentation & eLearning	37
	Scripting & Automation	38
Addit	ional Defect Fixes	39

Overview 5

### **Overview**



**Datamine Studio UG** meets all your underground design and data management needs.

Datamine's industry-leading systems form an unparalleled, integrated toolset for underground mine planning.

Studio UG is one of several products in the Studio product family, which includes:



Studio EM for exploration data analysis and modeling.



Studio Geo is for geological and structural modeling.



Studio Mapper for geological face mapping and reporting.



**Studio NPVS+** for strategic open pit optimization, design and enhanced scheduling.



**Studio OP** for open pit design and operational scheduling.



**Studio RM** for mine geology, reserve modeling and resource estimation.



**Studio Survey** for open pit and underground mine surveying and reporting.



**Studio UG** for underground mine design and scheduling.

**Note**: Studio UG release notes are cumulative for each major version, in reverse chronological order.

#### **Further Information**

Release notes for other versions of Studio UG are available via the Datamine Customer Support website. For more details, see <a href="https://www.dataminesoftware.com/support/">https://www.dataminesoftware.com/support/</a>.

For the complete Studio UG documentation, see <a href="https://docs.dataminesoftware.com/StudioUG">https://docs.dataminesoftware.com/StudioUG</a>.



## Studio UG 4.1 Release Notes

#### **DTS Compatibility**

**Studio UG 4.1** requires **Datamine Task Scheduler 4.1** or later to export and synchronize schedule data. The latest version of DTS is available from the Datamine Support Website and the Datamine Customer Portal.

#### **MSO 5.0**



**Mineable Shape Optimizer** (MSO) has been completely overhauled in this update to provide a more streamlined and intuitive wizard that guides you through the process of scenario and model setup, economics, framework orientation and configuration, shape control and reporting.

MSO continues to generate optimal stope shapes that match operational and geological constraints, and with version 5, setting up scenarios for parameter sensitivity analysis has never been easier. To that end, this update provides enhanced visibility throughout the stope optimization process without removing any of the granular controls that make MSO so powerful, making stope optimization more accessible to a wider audience.

This first version of the new MSO supports 2 Framework types:

- Slice
- Boundary

**Note**: The Prism framework option is not available in MSO 5.0 but will be added soon.


During the initial implementation phase - both "legacy" and "new" MSO are available via the **Report** ribbon.

For more information on MSO 5.0, including licensing, consult your online documentation and release notes at <a href="https://docs.dataminesoftware.com/">https://docs.dataminesoftware.com/</a>.

MSO is supported by an entirely new help file featuring screen overviews and learning activities. Press F1 on any MSO screen.

#### **Haulage Network Scheduling**

Traditionally, formulating dependencies that match haulage activities was achieved by creating manual or automated dependencies. A flexible system but time consuming for complex arrangements. Now, a new powerful 'Network' dependency rule facility lets Studio UG deduce the relevant dependencies from the presence, shape and configuration of design centre lines, saving time when preparing data for processing.



To support this, FXS design string direction validation options have been added to ensure the resulting strings describe a practical basis for scheduling activities, such as accurately representing the network formed between decline, level drive, ore drive and cross cut design definitions.

Where necessary, string interactions are formed automatically to reinforce the progression of activities, such as when an ore drive has multiple cross-cuts coming out of it, or when a stockpile comes out of a decline or any other drive. Road connections are formed based on your own connection tolerances.




As with other dependency configurations, network rules can be assigned per layer. Simple in its presentation (a new dependency rule and validation options) but powerful in how it automates the adjustment of design string data and defines dependencies automatically, providing significant time savings and consistent and repeatable results.

### **Dependency Animation**

Dependency data is now displayed during animation playback. As each segment of activity data displays, if a dependency is associated with its start time, the associated dependency information displays as well, unless hidden by **Sheets** or **Project Data** bar settings.

### **Preparation Panel**

The **Design** and **Definitions** panels are merged in this update, making design preparation tasks, including attribution and definition connection functions, accessible from the same area. This also means that you can edit attributes and apply design definitions without having to load and unload design data as in previous versions.




#### **Outline Validation**

Validation settings include new options for CXS design strings.

You can now check for excessive azimuth or dip changes around an outline and report design strings that violate these constraints during processing. This is provided courtesy of **Maximum Azimuth Change** and **Maximum Dip Change** settings in **Validation Options**.



#### **Leapfrog Data Import**



You can now import Leapfrog mesh (.msh) and Leapfrog Project Model (.lfm) files using a new Data Source Driver. Data is imported as wireframes.

If importing a Leapfrog Project Model file, you can choose to import all associated mesh data or a subset, and can choose the attribute to use to store the original mesh name, making downstream data management much easier.

The new formats are also supported by Studio's drag-and-drop facility, meaning you can drag one or more files into the 3D view and default load settings are used to create the relevant objects in memory and display them.

#### **Multiple File Loads**

You can now import or load multiple files in one operation using new multi-file options. Just pick the files you want to load using a simple browser, and Studio does the rest. You still get to specify load and importation settings, including those specific to a particular driver, but now you can complete the process in a fraction of the time.


To access this function, click **Add to Project** or **External** on the **Data** ribbon and pick your files.

Either import multiple files to the project or load them directly into memory. These files can be of the same type and format or different ones, meaning you can pick a batch of files of various formats (CAD, BMF, DMX and more) and either add them to the project or load and display them after importation and conversion. This makes light work of importing files from other projects and applications.

To use the previous driver selection method, use a menu option to pick a data type or select the new "by driver" option for project import.



#### **Legend Tools Update**



3D properties and similar screens now use a clearer and expanded toolset for legend management.

You can still display and edit legends as before, but now there is a dedicated button to create a new legend and (reinstating previous, reportedly popular behaviour) a new button appears to either select the current default legend for the selected column or set the current legend as the default for the current column (with no further prompts or popups).

We've also added the ability to add any colour chip to the unique legend item table in the New Legend Wizard

#### Geosoft® Driver

Geosoft Voxel Models files represent useful geophysical files, also known as *UBC* voxel models. These files contain geophysical inversion data. An import comprises 2 or more files - one file to define the geometry, and 1 or more files containing data values associated with the cells.


To support this new file type a new *Geosoft* option is available on the **Data Import** screen.

### **License Services Security**

At Datamine, we take the security and integrity of your data seriously.

License Services 7.0 is installed with your product update, and it provides additional security protection for client-server traffic.

You can now configure a license server to transmit and expect encrypted traffic. Utilizing the latest Transport Layer Security (TLS) protocol from Microsoft®, this level of data encryption helps prevent the interception and misuse of port traffic by malicious actors.



Server configuration can be completed in seconds (see above) and - providing connecting clients are running License Services 7.0 or above - client configuration is automatic; clients detect the current server mode and adjust their settings accordingly.

Legacy data mode is still supported; no server changes are necessary unless you want to change your data transmission protocol. Legacy License Services clients can connect to an upgraded (non-encrypted) server and vice versa.

You can find out more about these changes by searching for "License Services TLS Support" on the Datamine Support website, or by contacting your local Datamine office.

#### **Safer Scripting**


To maintain the highest level of local data security, we've rigorized our scripting interface in Studio products to provide a way to securely instantiate approved ActiveX objects through automation scripts. This provides a safer and more marshalled automation environment.




In brief, we've introduced a new Studio application method (CreateObject) that can be used in place of the deprecated <code>new ActiveXObject("Prog.ID");</code> instruction. A call to something like <code>window.external.System.CreateObject("Prog.ID");</code> allows approved ActiveX objects to be instantiated to support your scripts. Most importantly, the ones that provide the highest risk are blocked.

The **Datamine Studio Script Updater**, accessible via your **Home** ribbon, can update your scripts either individually or as a batch, automatically making them safer to use.

If you load a script that looks like it could benefit from additional protection, a banner appears atop your display area. This also provides access to the conversion utility:



#### **Ribbon Standardization**



Following your requests to adopt a more consistent ribbon layout between Studio products for core (shared) commands, we've made a few changes for this update. This means your familiarity with one Studio is now useful if using another product in the Studio range. Where possible, we have standardized command grouping and positions for the **Data**, **Format** and **3D View** ribbons. We've maintained specific layouts where a particular operating domain demands it, such as grade estimation, resource modelling, pit design and field mapping functions, so these aren't changing.

We will continue to standardize our ribbons, where appropriate, in future releases.

### **Other Command & Process Updates**

- COPYMOD now supports retrieval criteria.
- A new command digitise-doughnut lets you create data representing fully enclosed internal structures.



- smooth-gradient can now be used to fully smooth (start to end) preselected strings.
- REBLOCK now supports retrieval criteria
- INTEXT can now process data using either a data definition (INDD) file or a SETTINGS file, or neither.
- WIREFILL now supports retrieval criteria.


#### **Early Access Features**

#### **Advanced Digitizing Controls**

As part of a wider campaign to improve and extend our digitizing tools, we've introduced a new way of creating new string data in this update, and we'd love to know what you think before we finalize things.


new-string, arguably the most commonly used design command in any Studio product, has been extended over the years and also supported by a range of other design functions to enhance more 'managed' digitizing often required in the mine planning domain, where design drafting with precise string properties can be critical to an effective design and schedule. The extend-string command has been similarly enhanced.

new-string and extend-string can run in an enhanced mode in this update. By default, both commands behave as before, but there's a new project setting that allows advanced settings to be applied during digitizing to constrain the orientation of the next string segment you create. Located on the **Points and Strings** screen, check **Show advanced digitizing controls** to activate enhanced mode for **new-string** and **extend-string**:




The next use of either command displays a popup allowing you to constrain the length, azimuth and gradient of the next string edge. For constrained angle changes, you can also ensure azimuth changes are made in fixed amounts from the previous string segment:





This can help to ensure operational and design constraints are honoured during digitizing, saving time later by editing and adjusting design data. Help files for both commands have been updated to explain how to use the new controls. You can also press F1 when the new popup displays during digitizing.



Please let us know what you think of this early-access feature. We value your feedback!

## **All Improvements**

#### **Commands & Processes**

- **UG-4943** Studio UG now populates the "Originator" field in DTS whenever creating or updating a schedule for all tasks it creates/updates.
- UG-4941 When new tasks are added to DTS by UG they will now have X, Y, and Z values populated.
- UG-4880 Message boxes in Studio UG now support visual themes.
- UG-4850 An issue causing system instability when rerunning a validation has been resolved.
- UG-4763 In this version, the Design and Definitions screens have been merged into a new "Preparation" screen to streamline attribution and design definition configuration.
- UG-4557 The positioning of CXS activities has been improved.
- UG-3701 This update features the introduction of a new Haulage Network facility. Consult your help file for more details.
- UG-2072 A new 'Network Based Rules' dependency category has been created to support haulage scheduling in Studio UG.
- UG-1531 Dependencies are now displayed during animation playback.
- UG-463 Validation settings include new maximum azimuth and dip change options for CXS design strings.
- MSO-1559 MSO 5.0 is supported by an entirely new help file featuring screen overviews and learning activities. Press F1 on any MSO screen.
- MSO-1551 The Project Data bar has been updated to support MSO 5 workflow changes.
- CORE-9827 .dmx.tmp files are now ignored by the Project Files and Project
   Data control bars.
- CORE-9775 As part of the project to standardize some of the Studio ribbons, icon updates have been made.
- CORE-9732 Read-only DM files are now converted to read-only DMX files during project or utility-initiated conversion.
- CORE-9711 Documentation for EXTRA'S RAND and RANDBETWEEN numeric functions has been improved.
- CORE-9649 Block model fields in the Text Importer are now ordered more sensibly.

- CORE-9604 The default field of view angle for new projects is now 45 degrees (set-view-fov command).
- CORE-9586 To increase system security, we have blocked the display of online content in the Customization window.
- CORE-9583 In Files, Fields and Parameters screens running in Dark mode, text in dropdowns is now more readable.
- CORE-9579 COMPDH now supports up to 5 ZONE fields to composite within, and five optional fields DOM1 to DOM5 can now be specified to record dominant categorical values (by length) within each composited sample.
- CORE-9578 The Script Recorder now generates syntax that aligns with Datamine's safer scripting practices.
- CORE-9574The legacy script converter utility has been removed from product distributions.
- CORE-9561 Rationalization of baggage files for help systems means Studio installation file sizes are now smaller.
- CORE-9551 The Datamine Studio Script Updater has been provided to automatically convert your scripts to more protected versions.
- **CORE-9550** The Studio scripting environment now offers a safer scripting syntax, minimizing the potential impact of malicious thread actors.
- CORE-9546 New calculated (virtual) fields are now available to calculate the dip angle (\_PDIP) and direction (\_PDIPDIR) of the best fit plane through a data object.
- CORE-9542 A more secure mechanism for data object automation has been implemented. Consult your online help for more details.
- CORE-9540 You can delete selected 3D overlays of the Project Data using the <DELETE> key.
- CORE-9539 The CalculateEdgeMetrics() method now calculates values for the final edge of a closed perimeter.
- CORE-9528 The Plots window Section and View ribbons now have new icons.
- CORE-9526 It is now quicker to read and process DMX files containing alphanumeric columns.
- CORE-9522 WIREFILL now supports retrieval criteria.
- CORE-9521 COPYMOD now supports retrieval criteria.
- CORE-9519 REBLOCK now supports retrieval criteria.
- CORE-9490 The Text Importer can now be automated using any Studio product.



- CORE-9482 The switch-drillhole-points-traces command is now available on the Format ribbon (Display Mode group).
- CORE-9474 The Text Importer and INTEXT documentation has been extended and corrected.
- CORE-9473 INTEXT can now process data using either a data definition (INDD) file or a SETTINGS file, or neither.
- CORE-9449 The CENTRE file for the ELLIPSE process is no longer dependent on search, variogram or zone parameter file inputs.
- CORE-9409 An issue causing an unsorted block model to become locked after a previous attempt to load it has been resolved.
- CORE-9398 In COMPDH it has always been the case that if the LENGTH field in the input sample file is not equal to FROM - TO the LENGTH field is set to TO -FROM. This behaviour remains, but a maximum of 10 messages are issued in a process run.
- CORE-9383 The 3D View ribbon layout is now consistent between Studio products.
- CORE-9382 The Format ribbon layout is now consistent between Studio products.
- CORE-9378 The Data ribbon layout is now consistent between Studio products.
- CORE-9359 Your product now includes a new control bar: Project Data. This
  combines the power of previous bars to categorize and display files, loaded
  objects and plot data.
- **CORE-9391** When using the Text Importer, you can now import alphanumeric trace and absent values into a destination field that is numeric.
- CORE-9340 Unload all overlays of a specific data type using a new Sheets and Project Data control bar menu option.
- CORE-9301 Legend controls within various screens have been reverted to more popular legacy behaviour (with improvements) and restyled.
- CORE-9277 Quick Filter drop down lists now inherit the current look and feel theme.
- CORE-9252 Project data bar icons for the Plots and 3D folders have been updated.
- CORE-9233 By request, flat-rendered wireframes are now less shiny.
- CORE-9229 Text Importer scenario files (.dminsv) now appear in the Project Data control bar.



- CORE-9228 If opening a Text Importer scenario, file detection has been improved and you can now browse for missing files.
- CORE-9103 The Project Data, Loaded Data and Holes control bars now inherit visual themes.
- CORE-9097 An issue that could make data picking difficult where data was
  precisely coincident with the section plane has been resolved.
- CORE-9082 Drillhole Importer now recognizes "Hole\_ID" as a BHID mapping type.
- CORE-9014 All commands relating to the obsoleted **Visualizer** window have been removed from the application.
- CORE-8999 Tooltips have been added to the Group Lithology and Assign Lithology tasks.
- CORE-8980 When adding a new unique value legend item in the New Legend Wizard, you can now add any other colour to the current pallete.
- CORE-8839 Documentation on snapping to a grid has been improved.
- CORE-8805 File case names are now preserved in the default overlay when dragging and dropping files into the 3D window.
- CORE-8763 3D properties and similar screens now use a clearer and expanded toolset for legend management. See you help file for more details.
- CORE-8699 An issue causing the insert-by-segment-length to fail when working with large data has been resolved.
- CORE-8673 Issues causing unpredictable selection behaviour (or presentation of selected data) in the Plots window have been resolved.
- CORE-8654 Selecting the outer boundary of a plot sheet now enables the Manage ribbon (not the Home ribbon as previously).
- CORE-8625 Drillhole importer now recognizes more field names when automatically mapping to system fields.
- CORE-8519 Studio Data, Report and 3D View ribbons have been made standard in all Studio products other than Studio Mapper.
- CORE-8510 The Project Data control bar now displays files external to the project folder with the same vertical line indicator as the Project Files control bar.
- CORE-8196 MODSPLIT can now output either MODELOUT, FULLMOD or both. Previously, both outputs were always generated.
- CORE-8143 It is now quicker to close a project without saving it.



- CORE-7746 A new command digitise-doughnut lets you create complex string data in relation to an external perimeter and one or more closed internal strings.
- CORE-7506 The Drillhole Planner now inherits the current visual theme.
- CORE-7272 The Edge Editor is now available in this product. Use it to dynamically adjust string edges.
- CORE-6637 This update features early access to a preview of our advanced string digitizing controls. Constrain the azimuth, length and gradient of new string segments as you draw. Enable this beta functionality using the **Project** Settings screen.
- CORE-5878 The Project Data bar now permits multiple item selection.
- CORE-5550 smooth-gradient can now be used to fully smooth (start to end) preselected strings.
- CORE-1878 You can now import or load multiple files in one operation using new multi-file options.
- GEO-718 The layout of the **Drillhole Importer** screens has been improved.

### **Utilities & Supporting Services**

- CORE-9629 This update includes an upgrade to the mesh wireframing engine (2.0.2.54).
- CORE-9577 Your product installs a major update to License Services (7.0).
   This introduces encrypted traffic options for enhanced data traffic security.
- CORE-9536 The Start Page environment has been made more secure.
- CORE-9481 Data Source Drivers now export virtual data columns.
- CORE-9362 If using the DmFile SDK, reading and writing records is now twice as fast as before.
- CORE-8826 You can now import MineScape prism models where data overlaps in Z.
- **CORE-8524** An encrypted traffic option is now available to License Services server administrators. Requires a compatible client installation (7.0 or higher).
- CORE-8524 We have added a new driver! Import UBC voxel model data using the new Geosoft driver option.
- CORE-8160 The MineScape Block Model Importer has been added to the Data Import screen as a new driver: "MineScape strata model".
- CORE-6521 You can now import and load Leapfrog mesh and project model file data using a new Data Source Driver.



- MSO-1558 Documentation for MSO version 5.0 has been completed for this version.
- MSO-1581 Evaluation method descriptions on the **Report** screen have been updated for consistency and clarity.

### **Defect Fixes**

- UG-4889 MSO and Stope Recon ribbon buttons are now only available if a project is open.
- **UG-4875** An issue that could cause boundaries to be malformed, if FXS designs are segmented by number, has been resolved.
- UG-4862 Capitalization in the Flag Loaded Designs filter list is now consistent.
- **UG-4846** An issue causing the system to shutdown, if a design file becomes unavailable whilst the **Design** panel is open, has been resolved.
- UG-4832 An issue causing an "Index out of range" error when transferring data from Studio UG to EPS has been resolved.
- **UG-4826** An issue opening projects with saved histogram or stereonet chart plot items has been resolved.
- UG-4793 Changing a matching attribute removes previously matched designs correctly. Restoring the value now reprocesses them.
- UG-4784 Model evaluation no longer locks all models in the project, instead locking only the one targeted by the current evaluation.
- UG-4778 An issue that could cause system instability when validating a block model has been resolved.
- UG-4769 An unexpected validation failure error when converting model depletion rules has been resolved.
- **UG-4699** You can no longer create a property definition that is weighted by another already-weighted definition.
- UG-4512 Attribute values on retained activities are now updated correctly for CXS and WFM design data.
- CORE-9919 An issue causing system failure, if v1 or v2 commands were used in conjunction with plane alignment options, has been resolved.
- CORE-9875 An issue preventing the initial display of colour chips on the Assign Lithology screen has been resolved.
- CORE-9868 An issue causing Deswik import to fail has been resolved.
- CORE-9855 An issue causing issues when snapping and zooming in conjunction with vertical 3D scene exaggeration has been resolved.
- CORE-9826 An issue preventing the successful import of Deswik wireframe data has been resolved.
- CORE-9761 Picking of data symbols rendered in 2D in screen space can now be selected as normal.

- CORE-9745 An issue causing REBLOCK to delete the input block model, if additive fields are used, has been resolved.
- CORE-9717 The Project Data Bar's "Create from Loaded Data" menu option now works as expected.
- CORE-9716 Grids and Sections folders can no longer be removed from the Project Data bar.
- CORE-9714 An issue causing the incorrect rendering of 3D drillhole cylinders has been resolved.
- CORE-9710 Modeless dialogs are now reset as expected when a default profile is reinstated.
- CORE-9700 When translating strings, points or wireframes, decimal values now persist correctly between dialog sessions.
- CORE-9673 3D overlay group projections in Plots now react immediately to Project Data or Sheets control bar changes.
- CORE-9670 The UNFOLD wizard now has context-sensitive help.
- CORE-9653 When importing DXF/DWG points data, the 'Include Hatches' option is no longer displayed.
- CORE-9642 3D window axis and scale indicators now hide and show immediately following window configuration changes.
- CORE-9631 The INTEXT process no longer stalls indefinitely if settings are unexpected.
- CORE-9622 An issue causing SELWF to run more slowly than expected has been resolved.
- CORE-9618 An issue causing move-points to pick an incorrect target has been resolved.
- CORE-9615 An issue preventing the import of a Vulcan block model has been resolved.
- CORE-9613 An issue causing incorrect display of Information Mode output, if the 3D view was orthogonal to the active section, has been resolved.
- CORE-9595 The Command Toolbar contents are now more easily visible in Dark mode.
- CORE-9582 The Move String command is now available again on the ribbon.
- CORE-9562 Crash reports are now registering successfully in Freshdesk.
- CORE-9537 DMX files input to transform-coordinates now generates output files usable by Datamine Supervisor.



- CORE-9518 You no longer see an empty message box when trying to save an object to an open DMX file.
- CORE-9517 The Text Importer is now storing the Delimeter correctly if not a comma.
- CORE-9509 The Text Importer now reads fixed width values correctly.
- CORE-9503 "Ignore Clipping" instructions at the overlay level are now applied immediately.
- CORE-9499 An issue preventing string editing in plan view with >1 exaggeration in Z has been resolved.
- CORE-9419 The Point Cloud Reconstruction wizard now automatically generates a scenario on entering a new scenario name.
- CORE-9403 An issue causing the incomplete display of model cells in intersection at some section orientations has been resolved.
- CORE-9370 An issue causing unexpected data rounding in TRIFIL has been resolved.
- CORE-9357 WIREFILL now correctly interprets default plane information, and a @PLANE parameter is added to allow behaviour override.
- CORE-9353 An issue causing SELWF to fail when processing retrieval criteria has been resolved.
- **CORE-9348** The select-perimeter command no longer behaves inconsistently when called from a script.
- **CORE-9264** An issue causing incorrect IJK values to be generated via the Text Importer has been resolved.
- CORE-9236 An issue causing the incorrect alignment of a georeferenced image has been resolved.
- CORE-9231 An issue preventing the successful reinstatement of a UI profile has been resolved.
- CORE-9100 When transforming coordinates, and converting EPSG 5533 to WGS 84 and exporting to Earth, Lat/Long columns are no longer inverted.
- **CORE-9012** When transforming geographic coordinates, you can now generate output files on a non-primary drive.
- CORE-8952 The zoom command now accurately centers the screen if the scene is exaggerated.
- CORE-8794 An issue causing clipped block model data to be rendered invisible, when the clipping section deviates from the major axes, has been resolved.

- CORE-8696 An issue causing smooth-gradient (smg) to fail with a large string data file has been resolved.
- CORE-8632 Importing Deswik wireframe data now imports all available attributes. Previously some were not imported.
- CORE-8582 An issue causing unexpected view navigation in scenes with vertical (Z) exaggeration has been resolved.
- CORE-8259 3D window section clipping is now reapplied correctly when the section corridor width is changed.
- **CORE-8052** An issue causing **SAMPOUT** to be created incorrectly when writing alphanumeric fields has been resolved.
- CORE-7929 3D plot overlay labels now react to clipping settings as expected.
- CORE-6800 Studio now supports the concept of a temporary session-only data attribute.
- CORE-5413 REBLOCK no longer fails if there is a space in the file in the project folder.
- CORE-5270 Unable to cancel (ESC Key) Set Section about a single point
- CORE-5137 Adding a trailing space to a new project name no longer causes Studio to create 2 project folders.



## Studio UG 4.0.1 Release Notes

This is a hot fix patch for the previous 4.0 version and includes important fixes and improvements.

## **Improvements**

• CORE-9460 Saving block model data to the project is now much quicker.

### **Defect Fixes**

- CORE-9575 An issue causing TRIFIL to corrupt input data if forcibly closed early has been resolved.
- CORE-9541 An issue causing SLIMOD to fail with .dmx inputs has been resolved.
- **CORE-9507** An issue causing INPDDF to incorrectly generate a Datamine wireframe from Leapfrog ASCII data input, has been resolved.
- CORE-9501 Files created by the DMtoDMX conversion utility can now be loaded into Datamine Supervisor.
- CORE-9444 An issue causing clip-strings-to-wireframe to fail on some data has been resolved.
- CORE-9357 WIREFILL now correctly interprets default plane information, and a @PLANE parameter is added to allow behaviour override.
- CORE-8052 An issue causing SAMPOUT to be created incorrectly when writing alphanumeric fields has been resolved.

## Studio UG 4.0 Release Notes

## **Scheduler Compatibility**

**Studio UG 4.0** is released alongside (and requires) **Datamine Task Scheduler 4.0** to export and synchronize schedule data.


**DTS** is Datamine's platform for future scheduling functionality, replacing its predecessor, EPS. **DTS** represents the start of our ongoing campaign to provide best-in-field scheduling solution for mine planners.

**DTS** is available from the Datamine Support Website and the Datamine Customer Portal.

**Note**: This version of your product cannot connect to the legacy Enhanced Production Scheduler (EPS) product.

## **Key Improvements**

#### **New Datamine File Format**



The Datamine file format used natively by Studio products originated from Datamine's "Native File System" over thirty years ago. It has been maintained and supported by Datamine products since then. The mining industry has seen a significant increase in data volume and complexity during this time, which has started to strain the capabilities of the Datamine format.

Our response to this challenge is a new file format that is more suitable for the current and future data requirements of the mining industry. This format has a new file extension; .dmx.

Files are smaller and now supports up to 2048 columns. Your application generates .dmx files by default (this can be changed on the **System Options** screen. Both legacy (.dm) and new .dmx format files can be read. Other improvements will follow, as our new format is highly extensible and provides many opportunities to make data handling easier and smarter in the future.

The new format integrates smoothly with modern Studio products and your existing workflows and customization scripts, and the Table Editor can be used to view both legacy and new formats. For bulk file conversion, there's even a useful DM to DMX file conversion utility in the **Data Converter** installation folder should you wish to batch convert input files.

You can recognize .dm and .dmx files in the **Project Files** control bar:

•	.dmx file	A file in the proprietary .dmx Datamine binary file format.
<b>③</b>	.dm file	A file in the legacy .dm Datamine binary file format.

#### **Datamine Task Scheduler**

Studio UG integrates with **Datamine Task Scheduler** (DTS). In addition to the new name, **DTS** also features fixes made in response to feedback from the final version of EPS. Users of EPS will already be familiar with **DTS**. Whilst this version is mainly focused on rebranding, there are also useful improvements and fixes over the previous version of EPS.

Continuing on from its predecessor, **DTS** starts at version "4.0" (the last EPS version was 3.1). This also lines up with its partner products, Studio UG 4.0 and Studio OP 4.0.

**DTS** is supported by an updated version of the previous Datamine data viewer, now called **DTS InTouch**.


To make things easier during the transitional phase, the **EPS** panel features EPS project **upgrade** functions to automatically convert the .ews. schedule or .ewst schedule template file to the new DTS format, and continue synchronizing data.

**Note: DTS** operates with a new license, available from your local Datamine office.

**Note**: You cannot connect this or later versions of OP to the legacy EPS application, now discontinued.



#### **Stope Reconciliation Automatic Areas**



The **Stope Reconciliation** module can now discretize results per footwall, hangwall, sidewalls, backs and floor using a new *Automatic* **Area Wireframe Method**.

You can detect structures (areas) using a range of options (world axes, explicit azimuth and inclination or object attribute values). This can be useful for more detailed analysis between the blasted shape and the optimized shape from **Mineable Shape Optimizer** (MSO).

#### **Dependency Prefilter**


You can now control attribute-based and spatial dependencies by setting filters for both **FROM** and **TO** contexts, in addition to a new, general PreFilter. The initial filter can be used to refine the activities that will be used in processing the dependency rules. Data that passes a prefilter can then be further refined with the existing predecessor and successor filters if required. Any filter (prefilter, FROM or TO) can be set to *<no filter>* (the default setting).

#### Variable Autolayout Translations

You asked us to provide a way of applying variable translation distances for strings during autolayouts, so we extended the **Translate** autolayout rule settings screen to let you pick variable spacing, and set any number of successive translation distances for the output design definition.

We've done something similar with the **Create Multiple Lines** rule as well: Define successive string separation distances to create a custom repetition pattern.

#### **Plots Overhaul**




We've made major changes to the way plots are constructed with this update.

Plots are formed from a collection of plot items, ranging from 3D projections and associated sections, to clip art, text boxes and so on. You asked us to improve the usability of these tools so we've taken a step back and changed our approach to reporting. In a good way.

Plot items are now supported by their own ribbons, displayed whenever a particular plot item is selected, be that a projection, a north arrow, title box or whatever. With your help, we analysed the most commonly-used features and settings and have created a dedicated ribbon of tools for each plot item type. For example, managing the tabular contents of title box cells is now much easier thanks to handy cell managers.

The **Plots (Manage)** and **Plots (View)** ribbons have also been combined.


#### **3D Window Improvements**



The display of large data so that it has a lower impact on system and application performance. This includes new, smart settings to control how and when 3D scene data is rendered, making sure the system only has to draw what it needs to. To support these changes, new 3D options have been introduced to control **Environment Settings** (automated scene clipping) and a **Render on Demand** setting (on by default), added to the 3D system settings screen.

### **Filled Wireframe Intersections (Preview)**

We've added a new wireframe formatting option to the Wireframe 3D Properties screen: **Fill intersection**.




Wireframe data shown with standard clipping and filled intersection mode

Now, you can display clipped wireframes with solid intersections, emulating a 'filled' volume. This can be really useful when visualizing volumes in cross section.

**Note**: This feature is still in development, but we thought we'd let you have a look at progress so far. There are some limitations, such as viewing intersections of multiple coincident intersection planes of different colours, but it should give you an idea of what we're aiming for.

#### **Text Importer**



Import one or multiple text files using a new **Text Importer** screen.

Select as many files as you need to import and configure all importation options on a single screen, including automated and interactive field mapping for your selected data type and preview your file before you import.

Once you're happy with your settings (which can be set for each individual file if required), store your configuration information in a handy scenario file which can be used to consistently import data in the future and to share with others in your organization.

### **Datamine File Tags**

With the introduction of the new DMX file format in this version (see above), a new facility arrives for all users; table tagging.

We intend to make use of this new feature in the future, but you can also add your own data tags and values to any .dmx file using the Table Editor, which includes a new **Tag Editor** function on its toolbar:



Add as many tags and associated values as you like. This could be useful, say, to embed the status of a model or other design files, or to provide some implicit spatial context to data (mine, area, level, for example) without requiring additional data attributes.

#### **New Processes**

- **COMBTRI** allows up to 20 wireframe files to be combined in a single operation.
- INTEXT You asked for a file-based process to convert text files to Datamine files, so we created INTEXT. Either using the data definition specified in the incoming file, or by choosing the definition of another file, import text data using a range of options.



## **All Improvements**

#### **Commands & Processes**

- Multiple Cases Your product can now read and write the new Datamine binary format (.dmx) and will automatically convert non-default files in the project folder when a project is opened.
- Multiple Cases Your product has been updated to connect to DTS and DTS InTouch. This version cannot connect to EPS.
- Multiple Cases Several improvements and fixes have been made to improve 3D window visualization.
- Multiple Cases A new scenario-based Text Importer lets you import (single or batch) text files as a specified data type.
- **UG-4803** You can upgrade your legacy EPS schedule (.ews) and schedule template (.ewst) files using new conversion options on the DTS panel.
- **UG-4691** You can now specify variable translation distances for the Translate autolayout rule.
- UG-4474 The Create Multiple Lines autolayout rule has been extended to allow you to specify custom distances between strings.
- UG-4460 You can now control attribute-based and spatial dependencies by setting filters for both FROM and TO contexts, in addition to an initial activity PreFilter.
- **UG-4310** The name of the original planning model is now added to output block model and processed data tables.
- UG-4307 Stope reconciliation can now discretize results per footwall/hangwall/sidewalls/backs/floor using a new Automatic Area Wireframe Method.
- **CORE-9284** If you create a project using a folder that contains files in a non-native format, they are automatically converted.
- CORE-9265 By popular request, the "red" quick key combination now launches reduce-points (not simplify-string) as in previous versions. Menu options have also been reinstated.
- CORE-9240 Plot item locations now remain static when adjust the Relative positioning option for locatable plot items.
- CORE-9239 You can now interactively pick the target position of a locatable plot item using a new Anchor ribbon button.

- CORE-9234 DMX data saved from a Studio application now embeds the creating product and version as metadata (tags).
- CORE-9112 Studio project startups now include a check for local project files in a non-default format, and converting them to the default format.
- CORE-9021 Your product's Mesh wireframing library has been updated to version 2.0.1.53.
- CORE-9006 You can now use the "uc" quick key combination to apply clipping in Plots sheets.
- CORE-8938 A warning is now displayed when running HOLES3D when the BHID value in the Collar and Survey files doesn't match.
- CORE-8929 Loaded data objects that have metadata tags display those tags in the Properties control bar.
- **CORE-8918** Supporting plugins for PTCLD2WF and the Point Reconstruction Wizard have been updated.
- CORE-8906 Large Data Mode has been relabeled "Keep data in front of the camera" to make it clearer what it does.
- CORE-8895 In the Project files control bar, when using the context menu on a macro file that contains more than 9 macros, Studio doesn't crash and works as expected.
- CORE-8876 You can now choose to manually or automatically adjust 3D window clipping planes using the Environment Settings screen.
- CORE-8860 The "red" quick key combination now runs the simplify-string command, not the legacy reduce-points command. Ribbon access has also been updated.
- CORE-8702 query-angle now outputs angle information in degrees, minutes and seconds.
- **CORE-8697 intersect-drillholes-wireframes** now outputs the intersection angle between drillhole and wireframe.
- Cases: CORE-8490, CORE-8452, CORE-8357 Front & back 3D window clipping distances now computed automatically based on object's bounding box.
- CORE-8465 Context-sensitive Section and View ribbons now support projection editing and creation in the Plots window.
- CORE-8460The Plots (Manage) and Plots (View) ribbons have been combined.
- CORE-8424 Quick filtering wireframes and block models is now much quicker.



- CORE-8310 By default, data is now rendered in the 3D view only when required. This makes application usage with large data much quicker with more responsive controls.
- CORE-8216An Anchor ribbon has been introduced to support locatable plot items.
- CORE-8206 Reloading and refreshing large data objects is now quicker.
- CORE-8093 Improvements have been made to the way strings and points are rendered in the 3D window, to improve performance.
- **CORE-8047** Changes to the Plots ribbons will now be automatically shared with all Studio products, making forward development quicker and easier.
- CORE-8012 A new context-sensitive Text Cell ribbon has been created to modify the contents of text cells in title boxes.
- CORE-7966 You can now overwrite an existing legend instead of having to specify an unused/unique legend name.
- CORE-7946 Legend box plot item formatting can now be performed using a new Legend Box context-sensitive ribbon.
- CORE-7732 A new **Text Importer** screen lets you import multiple ASCII text files with per-file configurations and share your importation settings as a scenario.
- CORE-7694 Symbol plot item formatting can now be performed using a new Symbol context-sensitive ribbon.
- CORE-7693 Text Box formatting can now be performed using a new Text Box context-sensitive ribbon.
- CORE-7692 Title box formatting can now be performed using a new Title Box context-sensitive ribbon.
- CORE-7691 Scale bar formatting can now be performed using a new Scale Bar context-sensitive ribbon.
- CORE-7690 North arrow formatting can now be performed using a new North Arrow context-sensitive ribbon.
- CORE-7279 extend-segment-virtual-intersect can now be used on closed strings.
- **CORE-7161** The Create Model Prototype screen now has additional support for both new and copied rotated model prototypes.
- CORE-7051 COMPDH now lets you save residual composites to a new &RESIDUAL output file option.
- CORE-6906 When creating a ramp string, if the Distance set is less than the minimum segment length, a partial segment is added.

- CORE-2410 A new process INTEXT converts text files to Datamine files using an existing data definition and other parameters.
- CORE-231We've added a new wireframe visualization option; Fill intersection.
- **CORE-68** A new command **clip-strings-to-wireframe** lets you trim string data in relation to a wireframe surface or volume.

**Note: ESTIMA** and **ANISOANG** processes are no longer available in this product.

#### **User Experience**

- UG-4742 The planning ribbon now references DTS, not EPS.
- UG-4720 Visual formatting of Stope Reconciliation and planning task screens has been made consistent.
- **UG-4713** Mineable Reserves Optimizer has been removed from the Report ribbon.
- UG-4713 The Project Settings side bar now retains its visibility status between project sessions.
- CORE-9108 The Quick Filters screen now inherits the selected look and feel option.
- CORE-9086 The INTEXT text import process has been added to the Data ribbon
- CORE-9085 Combine Wireframes (COMBTRI process) has been added to the Wireframe ribbon.
- CORE-9084 Clip String to Wireframe has been added to the Digitize ribbon.
- CORE-8973 The Project Files control bar now differentiates .dm and .dmx formats by distinct icons.
- CORE-8937 The Project Files and Project Data control bars now display up to 30 macros in a .mac file.
- CORE-8935 A new splash screen has been implemented.
- CORE-8851 The Table Editor now supports visual themes.
- CORE-8765 The Georeference Objects screen now inherits current look and feel settings.
- CORE-8742 Images and colour scheme have been updated for the New Project Wizard.



- CORE-8601 The Project Data bar now displays the first level of available folders by default.
- CORE-5599 Managed task windows, such as implicit modelling and lithology assignment tasks, now persist their docked UI status between project sessions.

#### **Utilities & Supporting Services**

- CORE-8915 ALS Coreviewer options have been removed from this product. Datamine no longer resells ALS Coreviewer.
- Case: CORE-8759 End User License Agreement references have been replaced with Terms and Conditions.
- CORE-8747 You can now associate meta data with .dmx files using the Table Editor. This facility is not available for legacy .dm files.
- CORE-8585 You can now import up to 256 fields via the Surpac driver, and vou are alerted if this limit is exceeded.
- **CORE-8564** The obsolete command erase-wireframe-surface has been removed from the ribbon system.
- CORE-8488 Icons for the visualization window tabs and control bars have been updated.
- CORE-8439 A standalone utility has been created to convert .dm to .dmx files.
- CORE-8329 A new method more accurately calculates the volume of Prismatic models, as imported by the MineScape Importer utility (minescapeto-blockmodel command).
- CORE-6986 .xyz files can now be imported when importing Text files to the project.

#### **Documentation & eLearning**

 CORE-9348 EXTRA help files, including the examples topic, have been updated for clarity and consistent terminology.



## **Scripting & Automation**

• Multiple Scripted access to Datamine files has been extended to manage both legacy and new DMX file processes.

#### **Additional Defect Fixes**

- UG-4782 When loading and unloading dependencies manually (outside of the task), task buttons now update as expected.
- UG-4780 WFM designs that fail to process are now captured as expected when the <Failed Designs> filter is applied. CXS new designs are now captured correctly by the <New Designs> filter.
- UG-4741 Help menu tooltip capitalization has been standardized.
- **UG-4722** The Edit Filters apply button no longer remains enabled after a new system filter is added.
- **UG-4716** To ensure compatibility with DTS, you can no longer specify a unit for a Production Field leading with or comprising only of numeric characters.
- UG-4695 The Stope Reconciliation settings help file has been updated.
- UG-4689 Dominant field data is now exported correctly to .
- UG-4681 When exporting to a new schedule, the default number format now sets a limited number of decimal places as expected.
- **UG-4677** An issue preventing the generation of CXS designs in some situations has been resolved.
- **UG-4663** The Evaluation Legend selection now persists as expected when changes are made on the Evaluation Settings screen.
- **UG-4649** An issue preventing activities from being removed after deleting all designs, has been resolved.
- **UG-4648** Unexpected behaviour, after renaming a block model density field back to the default DENSITY, has been resolved.
- UG-4636 Project settings for Attributes, Properties, and Dependency Layers are now validated before attempting an export to DTS.
- UG-4561 The parent MSO folder of the Project Data control bar no longer displays an unnecessary item count.
- **UG-4514** The UG project file no longer appears in the All Files folder of the Project Files control bar.
- **UG-4375** In the Project Data bar, the Stope Reconciliation folder no longer displays an unnecessary Results subfolder.
- UG-4345 An issue causing unexpected zero grades for some activities in pivot tables has been resolved.
- CORE-9000 Enabling and disabling values in Assign and Group Lithology tasks now shows and hides drillhole intervals as expected.

- CORE-8947 1-letter macro file names now appear in the Project Files control bar as expected.
- CORE-8947 SELWF now produces expected results when there are spaces in the field name values of ZONE.
- CORE-8867 An issue preventing the successful installation of License Services on some Windows Server platforms has been resolved.
- CORE-8848 The double-sided 3D wireframe rendering setting is now correctly saved to the project.
- CORE-8811 An issue caused by swapping Snap Mode settings has been resolved.
- CORE-8801 An intermittent issue affecting file lookups when running macros has been resolved.
- CORE-8784 Wireframes generated by SWATHPLT now include consistently oriented triangles.
- CORE-8783 Making a plot item locatable no longer unexpectedly changes that plot item's position.
- CORE-8757 An issue causing PPQQPLOT to fail with a large input file has been resolved.
- CORE-8754 An issue causing system shutdown after reordering georeferencing table values (georeference-objects), has been resolved.
- **CORE-8675** An issue causing **converge-segments** to display unexpected results after undoing the operation has been resolved.
- CORE-8670 The BOOLEAN process no longer fails when the two inputs (in the same run) have a column with the same name but a different data type.
- CORE-8610 3D object bounding boxes, used for 3D view configuration are now set correctly for all string object entities.
- CORE-8583 An issue causing an orthographic 3D view corruption where the front clipping plane distance is very large, has been resolved.
- CORE-8530 An issue causing system instability, when clipping in the Plots window using a quick key, has been resolved.
- CORE-8523 An issue attempting to print screen contents when Info Mode is active has been resolved.
- CORE-8479 In Plots, setting a primary clipping width to a value larger than the
  extent of the section no longer causes the midpoint to be moved outside of
  the section extents.
- CORE-8475 An issue causing unexpected behaviour when snapping at high zoom levels has been resolved.



- CORE-8087 An issue that could cause a progressive memory leak when reloading a data object has been resolved.
- CORE-7713 An issue preventing the automatic generation of legends by data type has been resolved.
- CORE-7645 HOLES3D now considers dip and bearing information from both a survey and collars file, prioritizing the survey file information. DIPMETH is applied to all data, regardless of source.
- **CORE-6591** A repetitive warning message in Table Editor relating to undo operation performance can now be disabled as expected.
- CORE-6002 An issue preventing the update of associated screens after renaming 3D overlays has been resolved.
- CORE-3477 You can now generate a 2 point vertical plane by selecting 2 vertically-aligned points.







Datamine enables efficient and sustainable mining through the application of world-leading technology and services.

## **Read the Docs**

docs.dataminesoftware.com

# **Get in Touch**

www.dataminesoftware.com/contact www.dataminesoftware.com/support







